Search ...

## Seize fsmo when primary domain controller is dead

Goto secondary domain controller and execute **ntdsutil** in dos.

```
ntdsutil: roles

fsmo maintenance: connections

server connections: connect to server XXX.domain.com (secondary DC)

server connections: quit

fsmo maintenance: ?

fsmo maintenance: seize RID master

(Yes on popup window)

fsmo maintenance: Seize infrastructure master

(Yes on popup window)

fsmo maintenance: Seize naming master

(Yes on popup window)

fsmo maintenance: Seize PDC

(Yes on popup window)
```

Check if all the roles are correctly assigned to new server.

```
netdom query fsmo
```

Complete the seizing process by removing the dead server.

```
ntdsutil: metadata cleanup
metadata cleanup: connections
server connections: connect to server xxx.domain.com
server connections: quit
metadata cleanup: select operation target
select operation target: list domain
select operation target: select domain 0
select operation target: list sites
select operation target: list sites
select operation target: list servers in site
select operation target: list server X (dead server)
select operation target: quit
metadata cleanup: remove selected server
(Yes on pop-up window)
```

Your email address will not be	published. Required fields are marked *		
Type here			
			4
Name*	Email*	Website	

Copyright © 2023 console.kim.sg

Active Directory Sites and Services > Sites > Default > Servers > delete the dead server

If the dead server hardware is revived, remove Active Directory

Yes on pop-up windows and reboot the server for workgroup  ${\color{red} {\mathfrak G}}$ 

Cmd > dcpromo /forceremoval